

OpenEMR 3.0.1 Appliance Manual

Page Last modified: 04/11/09 03:06:44 AM

[LINK TO MANUAL IN PDF FORMAT](#)

Author: Brady Miller

Email: brady@sparmy.com

Discussion Board: http://sourceforge.net/forum/?group_id=60081

OpenEMR 3.0.1 Appliance Manual Table of Contents

Introduction	3
Online Demo	4
Download the OpenEMR Appliance and VMware Player	5
Start the OpenEMR Appliance	5
Windows	5
Linux	7
Using the OpenEMR Appliance	9
Using OpenEMR Appliance	9
OpenEMR User Training	11
Helpful Tips	11
List of Login Names and Passwords	12
Configuration of the OpenEMR Appliance	12
OpenEMR Visual Layout Configuration	12
Pharmacy Dispensary Module Configuration	16
Printer Setup	19
Email Server Setup	27
Backup (Automatic) Setup	42
Static IP Address Setup	45
Change Clock	55
Change Appliance Password	58
Reboot or Shutdown Appliance	62
Desktop Installation	65
Instructions for Building the OpenEMR Appliance	66
Software	66
Install the Ubuntu 8.04 Server Virtual Computer	66
Configure PHP and Apache (with SSL)	98
Install OpenEMR 3.0.1	99
Install and Configure Webmin	110
Configure Firewall	114
Finishing Touches On Appliance	125
Appendix	137
A. Configuring client web browser for https	137
B. Useful Websites	142
C. Author Email and License/Disclaimer	143

Introduction

[Main TOC Link](#)

The clinical benefits of computerized medical records are clear, however, the costs of current proprietary systems are large. This high cost precludes many small practices from transitioning to computerized medical records. Open Source medical record systems are quickly becoming a viable, cost effective alternative.

The goal of this project is to maintain a comprehensive Open Source Medical Practice Management Software Appliance, which provides office scheduling, electronic medical records, prescriptions, insurance billing, accounting, and access controls. This appliance has many possible applications, such as a fully functional demo, a testing/developing platform, and as the starting point in real world clinic applications. It can be run on any operating system that supports the *VMware Player*. The detailed building instructions of this appliance are also included in this manual, which will allow easy modification/updates of appliance and will allow simple transition to a native server, if required.

This version of the OpenEMR Appliance is markedly different than previous versions. OpenEMR is now installed on the Ubuntu 8.04 Server Edition operating system, and is a vast improvement over the previous Mandriva operating system. For users whom require a GUI desktop, the Ubuntu Server edition OS (8.04) does not come with a desktop, however it is easy to install and is described in this manual. The administration in the Ubuntu Server can be mostly done via Webmin, which is described in this manual.

This manual contains instructions on downloading, starting, and using the OpenEMR Appliance, OpenEMR user manual web links, helpful tips on OpenEMR use, instructions for configuration and administration of the Appliance, and full detailed instructions on how the Appliance was built.

The *Download the OpenEMR Appliance and VMware Player* chapter contains how and where to download software from.

The *Start the OpenEMR Appliance* chapter contains information on starting the OpenEMR Appliance.

The *Using the OpenEMR Appliance* chapter contains information on how to use the OpenEMR Appliance, web links to User Manuals, helpful tips, and all the login names and passwords that will be needed while using the appliance.

The *Configuration of the OpenEMR Appliance* chapter describes how to configure and administer OpenEMR and the appliance. There are instructions

describing how to set up a printer, an email server, and an automated backup scheme. This chapter also describes how to choose the visual layout of OpenEMR and how to add the pharmacy dispensary module along with other instructions on setting up a static IP address, installing a desktop environment, setting the time, changing the password, and safely shutting the appliance down.

The *Instructions for Building the OpenEMR Appliance* chapter describes in detail how this Appliance was built.

Online Demo

[Main TOC Link](#)

Here are online demos of the OpenEMR 3.0.1 appliance:

With the new frames look:

<http://OpenSourceEMR.com:2090/openemr/> (Main OpenEMR program)

With the traditional look:

<http://OpenSourceEMR.com:2091/openemr/> (Main OpenEMR program)

These are fully functional demos, which allows you to play around with all the software packages in the appliance. It uses all the same logins and passwords as the appliance(refer to '[Login Name and Password](#)' section). The OpenEMR users were added to demonstrate the access controls:

-Login name-----Password-----Description

1. admin_____pass_____Administrator
2. physician_____physician_____Physician(more access than clinician)
3. clinician_____clinician_____Clinician(less access than physician)
4. accountant_____accountant_____Accountant
5. receptionist____receptionist____Front desk receptionist

Don't worry about breaking it, because it resets itself to its original state every day at 8:00AM(new frames appliance) and 9:00AM(traditional look appliance) Pacific Time. Have fun. (If demo is not working email me at brady@sparmy.com)

Download the OpenEMR Appliance and VMware Player

[Main TOC Link](#)

1. Download and install the FREE VMware Player at:
<http://www.vmware.com/products/player/>
2. Download the FREE OpenEMR Appliance.
 1. You can download Appliance via Direct Download or Torrent (file is 760MB, which extracts to 2GB):
 1. Direct Download from Sourceforge:
http://sourceforge.net/project/showfiles.php?group_id=167832
 2. Torrent file link: <http://www.bradynd.com/OpenEMR-3-0-1-appliance-1.torrent> (If you need a torrent software client, then try: <http://azureus.sourceforge.net/>)

Start the OpenEMR Appliance

[Main TOC Link](#)

Windows

[Main TOC Link](#)


1. Unpackage the OpenEMR-3-0-1-appliance-1.zip file.
2. Run VMware Player (screenshot below).



3. Start up the OpenEMR Appliance by opening the OpenEMR-3-0-1-appliance-1.vmx file in the VMware Player.
4. If this is your first time starting the OpenEMR Appliance, then a window will pop up (see screenshot below). Select 'I copied it' and click the 'OK' button.



5. Several windows may also pop up explaining that certain drives or sound drivers are not gonna work. Just click 'ok' and continue.
6. Ubuntu will now boot up, just give it some time. After boot up you will see the following introduction screen:



```
OpenEMR-3-0-0-appliance-1 VMware Player ▾ Devices ▾
* Running local boot scripts (/etc/rc.local) [ OK ]

Welcome to the OpenEMR Appliance!!

Most Recent User Manual can be found at http://bradynd.com/appliance

The IP address of this appliance is: 192.168.1.144
OpenEMR -> https://192.168.1.144/openemr   user: admin   pass: pass
Webmin -> https://192.168.1.144:10000/   user: openemr pass: openemrcool

The HTTPS(443), SSH(22), and Webmin(10000) ports are open.

Appliance login name is openemr with password openemrcool
To run a command as administrator (user "root"), use "sudo <command>".
sudo command password is openemrcool

MySQL user is openemr with password openemr
MySQL root user has an empty password
(Note that the above passwords are from initial configuration)

Software version information: Ubuntu Server Edition 8.04, OpenEMR 3.0.0, Webmin
1.450, Apache 2.2.8, MySQL 5.0.51a, and PHP 5.2.4.

openemr login: _

To direct input to this virtual machine, press Ctrl+G.
```


This is the introduction screen. Note that it automatically displays the IP address of your appliance, along with links to OpenEMR and Webmin. These links are customized for you depending on your IP address. The initial important user names and passwords are also displayed. To use appliance, proceed to the '[Using the OpenEMR Appliance](#)' section below.

Linux

[Main TOC Link](#)


1. Unpackage the OpenEMR-3-0-1-appliance-1.zip file (use the 'unzip OpenEMR-3-0-1-appliance-1.zip' command).
2. Run VMware Player.
3. Start the OpenEMR appliance by opening the OpenEMR-3-0-1-appliance-1.vmx file in the VMware Player.

4. If this is your first time starting the OpenEMR Appliance, then the below window will pop up:



You will only see this window the first time you start the appliance. Click 'Create'.

5. Several windows may also pop up explaining that certain drives or sound drivers are not gonna work. Just click 'ok' and continue.
6. Ubuntu will now boot up, just give it some time. After boot up you will see the following introduction screen:



```
OpenEMR-3-0-0-appliance-1 VMware Player ▾ Devices ▾
* Running local boot scripts (/etc/rc.local) [ OK ]

Welcome to the OpenEMR Appliance!!

Most Recent User Manual can be found at http://bradynd.com/appliance

The IP address of this appliance is: 192.168.1.144
OpenEMR -> https://192.168.1.144/openemr user: admin pass: pass
Webmin -> https://192.168.1.144:10000/ user: openemr pass: openemrcool

The HTTPS(443), SSH(22), and Webmin(10000) ports are open.

Appliance login name is openemr with password openemrcool
To run a command as administrator (user "root"), use "sudo <command>".
sudo command password is openemrcool

MySQL user is openemr with password openemr
MySQL root user has an empty password
(Note that the above passwords are from initial configuration)

Software version information: Ubuntu Server Edition 8.04, OpenEMR 3.0.0, Webmin
1.450, Apache 2.2.8, MySQL 5.0.51a, and PHP 5.2.4.

openemr login: _
To direct input to this virtual machine, press Ctrl+G. vmware
```

This is the introduction screen. Note that it automatically displays the IP address of your appliance, along with links to OpenEMR and Webmin. These links are customized for you depending on your IP address. The initial important user names and passwords are also displayed. To use appliance, proceed to the '[Using the OpenEMR Appliance](#)' section below.

Using the OpenEMR Appliance


[Main TOC Link](#)

Using OpenEMR Appliance

[Main TOC Link](#)

1. You connect with the OpenEMR Appliance through a web browser. You can get the Appliance IP address along with links to OpenEMR and Webmin on the above [introduction](#) screen. Use those links as the web address on another computer's web browser. (If you get a security error in your web browser, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)

1. OpenEMR at https://Appliance_IP_address/openemr



2. Webmin at https://Appliance_IP_address:10000/



3. For the list of application login names and passwords go to the '[Login Name and Password](#)' section below.
2. You can also change your IP address to a static one, so it doesn't change after your virtual server is turned off or re-started. Directions to do this are in the '[Static IP Address Setup](#)' section.

OpenEMR User Training

[Main TOC Link](#)

1. There is an excellent OpenEMR wiki at: <http://www.oemr.org/modules/wiwimod/>
2. There is an excellent web site for learning how to use all of the components of OpenEMR at: <http://www.oemr.org/modules/cjaycontent/index.php?id=2>
3. You can ask question at the SourceForge OpenEMR forum at: http://sourceforge.net/forum/?group_id=60081
4. The OpenEMR home page is here: <http://www.oemr.org/>
5. The most current version of this appliance user manual will hopefully always be available at: <http://www.bradymd.com/appliance>
6. There is also an older user manual in the `/var/www/html/openemr/Documentation` directory which can be helpful.

Helpful Tips

[Main TOC Link](#)

1. **NEED** to ensure clock is set correctly (Virtual computer time should not differ from the host computers, or there will be cron scheduling problems)

List of Login Names and Passwords

[Main TOC Link](#)

1. Ubuntu user -> user: 'openemr' password: 'openemrcool'
2. Ubuntu sudo command -> password: 'openemrcool'
3. Webmin -> user: 'openemr' password: 'openemrcool'
4. OpenEMR -> user: 'admin' password: 'pass'
5. MySQL user -> user: 'openemr' password: 'openemr'
6. MySQL admin -> user: 'root' NO PASSWORD


Configuration of the OpenEMR Appliance

[Main TOC Link](#)

OpenEMR Visual Layout Configuration

[Main TOC Link](#)

1. OpenEMR has three visual layouts to choose from; the traditional layout, a frames layout with radio buttons, and a frames layout with a tree view menu. We will first show screenshots of the available layouts, and then will show how to configure this option.



Traditional view (also called old-style layout).

OpenEMR - Mozilla Firefox

File Edit View History Delicious Tools Help

OpenEMR

Logged in: Administrator (Default) Active Patient: None March 1, 2009

Top Bot

- Calendar
- Password
- Admin
- Reports
- Ofc Notes
- Fax/Scan
- Addr Bk
- Chart Trk
- Billing
- Superbill
- AuthNotes
- New Pt
- Patient
- History
- Encounters
- New Encntr
- Rx
- Issues
- Immunize
- Documents
- Pt Report
- Pt Notes
- Transact
- Summary
- Encounter
- Charges

Active Patient: None
Active Encounter: None

Find
by: Name ID
 SSN DOB

Logout


All Users 2009-03-01 Day View Go Today Add Search
Administrator All Facilities << Sunday, March 1, 2009 >>

Administrator	
8:00	IN
8:15	
8:30	
8:45	
9:00	
9:15	
9:30	
9:45	
10:00	
10:15	
10:30	
10:45	
11:00	

Patient Notes (See All) and Authorizations (More)

Done 192.168.1.131

Frames with navigation by radio buttons.



Frames with navigation by a tree view menu.

2. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then type in your user password):

```
#edit the file /var/www/openemr/interface/globals.php:
sudo jed /var/www/openemr/interface/globals.php
#change below bolded number to desired layout :
// Set this to 1 or 2 to activate support for the new frame layout.
// 0 = Old-style layout
// 1 = Navigation menu consists of pairs of radio buttons
// 2 = Navigation menu is a tree view
//
$GLOBALS['concurrent_layout'] = 1;
TEXT EDITOR SAVE AND EXIT
```


Pharmacy Dispensary Module Configuration

[Main TOC Link](#)

1. The pharmacy dispensary module will allow you to dispense and keep track of your own med/herbs/supplement dispensary. It will also create bottle labels of the drugs you dispense.
2. Turn on the pharmacy dispensary module in the OpenEMR configuration file. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then type in your user password):

```
#edit file /var/www/openemr/interface/globals.php:  
sudo jed /var/www/openemr/interface/globals.php  
#edit the following bolded variable :  
$GLOBALS['inhouse_pharmacy'] = true;  
TEXT EDITOR SAVE AND EXIT
```

1. Here are some quick OpenEMR screenshots (note these were taken from version 2.8.3 with the Traditional View) that show how to navigate to the pharmacy dispensary module for administrative purposes:



Click 'Administration'

Users & Groups Forms Practice Calendar Database BatchCom **Drugs** Language Logs Back

Logged in: Clinical Director Sun September 9th 2007

User & Group Administration

New Facility Information:

Name: Phone:
 Address: Fax:
 State: City:
 Country: Zip Code:
 Federal EIN:

Add

Edit Facilities: Main Clinic(Edit)

New User:

Username: Password:
 Groupname: Healthy Choice Clinic Authorized:
 First Name: Middle Name:
 Last Name: Default Facility: Main Clinic
 Federal Tax ID: Federal Drug ID:
 UPIN: See Authorizations: None

Additional Info:

Add

New Group:

Groupname: Initial User: admin Add

Click 'Drugs'.

Users & Groups Forms Practice Calendar Database BatchCom **Drugs** Language Logs Back

Logged in: Clinical Director Sun September 9th 2007

Name	NDC	Form	Size	Unit	Add	Lot	QOH	Expires
Add Drug								

Click 'Add Drug', enter stuff and play around to figure out how to use.

Quick OpenEMR screenshots of prescribing drugs with the dispensary:

Summary History Encounter Transaction Documents Report Close Popups

Robert Crawford (ID: 1, DOB: 1974-02-12, Age: 33, Home: 123-214-3543) **Logged in as: Clinical Director EncounterSun A**

This Encounter for Robert Crawford:

Clinical Director SOAP **Subjective:** Itchy foot
Objective: red foot
Assessment: athletes foot
Plan: anti-fungal cream

Clinical Director Patient Encounter

category

Coding

- Superbill
- ICD9 Search
- CPT4 Search
- HCPCS Search
- Copay
- Other

Prescriptions

- List Prescriptions
- Add Prescription 

Billing (More) Justify

[Receipt]

CPT4 **5466** Foot Rub 2200.00
(416.0)
total: 2200.00

ICD9 **416.0** Prim Pulm Hypertension

Click 'Add Prescription'.

Summary History Encounter Transaction Documents Report Close Popups

Robert Crawford (ID: 1, DOB: 1974-02-12, Age: 33, Home: 123-214-3543) **Logged in as: Clinical Director EncounterSun A**

This Encounter for Robert Crawford:

Clinical Director SOAP **Subjective:** Itchy foot
Objective: red foot
Assessment: athletes foot
Plan: anti-fungal cream

Clinical Director Patient Encounter

category

Coding

Superbill
ICD9 Search
CPT4 Search
HCPCS Search
Copay
Other

Prescriptions

List Prescriptions
Add Prescription

Starting Date: September 09 2007
Provider: Clinical Director
Drug: Drug Lookup
 in-house -- or select from inventory --
Quantity:
Medicine Units:
Take: in
Refills: 00 # of tablets: 0
Substitution: substitution allowed
Notes:
Add to Medication List: No Yes
 units, \$

Billing (More) Justify

[Receipt]
CPT4 5466 Foot Rub 2200.00
(416.0)
total: 2200.00
ICD9 416.0 Prim Pulm Hypertension

Note the things circled in red, which are part of the pharmacy dispensary module. Note that in version 3.0.1 the 'Prescribe and Dispense' button is now labeled 'Save and Dispense'.

Printer Setup

[Main TOC Link](#)

1. For USB printers, you will need to connect the device by clicking on printer on top of window. Your host computer may no longer be able to see the printer after this step(not permanent, but can be a pain).



In this case I click on the 'Hewlett-Packard...' button at top of VMware

window.




This is just to demonstrate that the 'Hewlett-Packard...' button is now shaded.


2. Now, you need to add the printer . It would be great if we could add and administer the printer through webmin, but I was unable to get this to work. So we will add a new printer to CUPS directly. To do this, we will actually use a text based browser from the commandline (yes, you are now entering nerd world). Enter below **bolded** instructions on command line:

```
#open up web page with text based browser (use up/down  
arrow keys or 'tab' key to scroll thru links and hit 'enter'  
key to select a link)
```


```
lynx http://localhost:631
```




Select 'Administration'.




Select 'Find New Printers'. (it will take a bit of time to load next page)



Select the printer you want to add.




Follow instructions to fill out 'Name:', 'Location:', and 'Description:' fields. Then select 'Continue'. (it will take a bit of time to load next page)




Choose the 'Model:' (use right-arrow key to show the menu after you select this field). Then select 'Add printer'. (it will take a bit of time to load next page)



Enter username 'openemr'.



Enter your 'openemr' user password.




Shows printer was successfully added. Type 'q' to quit.

3. Now that the printer has been added, we can print a test page and learn how to administer the printer. Again, it would be great if we could do this through Webmin, but I was unable to get this to work. So we will go back to using CUPS directly through our text-based browser.

#open up web page with text based browser (use up/down arrow keys or 'tab' key to scroll thru links and hit 'enter' key to select a link)

lynx <http://localhost:631>




```
OpenEMR-3-0-0-appliance-1 VMware Player Devices
Common UNIX Printing System 1.3.7
Home Administration Classes Documentation/Help
Jobs Printers
Welcome!
These web pages allow you to monitor your printers and jobs as well as
perform system administration tasks. Click on any of the tabs above or
on the buttons below to perform a task.
Help Add Class Add Printer Manage Classes Manage Jobs Manage Printers
Manage Server
If you are asked for a username and password, enter your login username
and password or the "root" username and password.
About CUPS
Happy Computer and Printer CUPS provides a portable printing layer for
-- press space for next page --
Arrow keys: Up and Down to move. Right to follow a link; Left to go back.
H)elp O)ptions P)rint G)o M)ain screen Q)uit /=search [delete]=history list
To direct input to this virtual machine, press Ctrl+G
```

Select 'Printers'



Use down arrow key to scroll below the shown printer.



Select 'Print Test Page' (also note all the other administration options in case you need them in the future).

```
OpenEMR-3-0-0-appliance-1 VMware Player Devices
Print Test Page - CUPS 1.3.7
REFRESH(2 sec): http://localhost:631/printers/Brother_MFC-7840W_USB_1
Print Test Page
Home Administration Classes Documentation/Help
Jobs Printers
Test page sent: job ID is Brother_MFC-7840W_USB_1-3.
The Common UNIX Printing System, CUPS, and the CUPS logo are trademarks
of Apple Inc. CUPS is copyright 2007-2008 Apple Inc. All rights
reserved.
Commands: Use arrow keys to move, '?' for help, 'q' to quit, '<-' to go back.
Arrow keys: Up and Down to move. Right to follow a link; Left to go back.
H)elp O)ptions P)rint G)o M)ain screen Q)uit /=search [delete]=history list
To direct input to this virtual machine, press Ctrl+G
```


Confirmation of print job is shown. A test page should be sent to your printer. Type 'q' to quit. You are now officially a nerd.

Email Server Setup

[Main TOC Link](#)

1. This will allow only locally produced emails (such as “status” emails during the below 'backup script' and emails originating from OpenEMR for appt confirmations) to be sent over the internet.
2. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then type in your user password):

```
#log into root
sudo aptitude install postfix
```



-Hit 'tab' key to select 'Ok'.



Select 'Internet Site', then select 'OK'.




Enter the domain name that is put in the from field of your outgoing emails, for example ouroffice.com . (don't worry, this can always be changed after installation). Then select 'OK'.

3. Now we can configure the mail server in Webmin. First we will start the Postfix module in Webmin, and then we will configure it. Point a web browser outside your appliance to the Webmin link reported in your appliance [introduction](#) screen.


(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)




Login.




Click 'Webmin'.




Click 'Webmin Configuration'



Click 'Webmin Modules'.




Toggle on 'From ftp or http url', then enter 'http://www.webmin.com/updates/postfix-1.450-1.wbm.gz'. Then click 'Install Module'. (We can't use the usual standard postfix module because of a bug in mail aliases).



Confirmed successful installation. Then click 'Postfix Mail Server'.



Click 'General Options'.



Sorry about the poor quality screenshot. Only several changes need to be made here (circled in red), which are all detailed directly below.


- 1) In 'Send outgoing mail via host', type your outgoing smtp mail server here (this should be given by your internet service provider).
- 2) In 'Local networks', toggle on 'Default'.
- 3) In 'Automatic local networks', choose 'Local machine only'.
- 4) Click the 'Save and Apply' button.



Click 'Mail Aliases'.



Click 'root'.




This is where you can direct all the administrative messages created by


your appliance to your email address. Enter your email address in the field circled in red. Then click 'Save'.




It worked, click 'Return to Postfix Configuration' to restart Postfix.




At bottom of page click 'Stop Postfix'.



At bottom of page click 'Start Postfix'.



Click 'Refresh Modules'.



After done, then refresh browser (this will place a postfix link into Webmin's menu in the 'Servers' section).

4. You are now done. For the future you can now get to the postfix configuration menu in Webmin in the 'Servers' section.

Backup (Automatic) Setup

[Main TOC Link](#)

1. Automatic backups are extremely important. There are numerous strategies and tools to do this. You can back up the entire appliance (turn it off first), you can use tools in Webmin, or you can use scripts/tools in linux. There is no absolute right way to do it (many administrators will employ more than one mechanism), but you have to do it. Imagine the horror if you walked into your clinic one day, and all of your data was gone. Considering the sensitivity of data, it is also a good idea to consider encryption with some backup schemes. The things that need to be backed up in the OpenEMR 3.0.0 Appliance are the openemr MySQL database and the openemr web directory.

2. The script provided will enable a daily backup of the openemr database in the MySQL server and the OpenEMR web directory. The script will place a non-encrypted backup in the local hard drive secured /backup directory, and will also copy an encrypted backup to a DVD. The DVD copy works via multi-session, so you basically just need to leave one DVD in the DVD writer until it fills up. Do NOT use RW DVD. This script will work and should be used with R only DVD's. The output of the automated backup script will be emailed to the person's email entered in above email server setup.
 1. The local /backup directory will have to be manually cleaned up occasionally. I'd recommend deleting old backup sub-directories on a monthly basis or so. (of course, a script could be written for this)
 2. There is no restore script yet, will have to be done manually.
 3. The MySQL database is gzipped and the OpenEMR web directory is tarred and gzipped.

3. Configure file encryption package:

1. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then type in your user password):

#Configure file encryption. If you want to be able to decrypt your encrypted files you need to remember (case sensitive) the passphrase that you type below. I'd also remember all the other info you type below.

cd /home/openemr

sudo gpg --gen-key

-'ENTER' to default of 1 for key selection

-'ENTER' to default 2048 keysize bits

-'ENTER' to default '0' so key does not expires

-Type 'Y' to confirm above

-Type your real full name

-Type your real email address

-Type 'openemr secure backup key'

-Type 'O' to confirm

-Type a very secure and long 'passphrase' (the longer your passphrase is the more secure, go for at least 15 characters with numbers, different cases, and strange characters)

#IMPORTANT!!! You **NEED** to backup the entire contents of directory **/home/openemr/.gnupg** on the most indestructible disk(s) you can find and then keep in a secure place. This directory contains your secret key file, and without this you will be unable to restore from your encrypted data backup!!! You also need to **remember** your **passphrase**, or you won't be able to restore your backed up data.

#The decrypt command, in case you need at some point:
#`gpg -o OutputFilename -d InputFilename`

4. Configure backup script and automate it:

1. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then type in your user password):

```
#install the DVD burner software  
sudo aptitude install dvd+rw-tools  
-y to packages
```

```
#create a secure backup directory  
sudo mkdir /backup  
sudo chown root:root /backup  
sudo chmod 700 /backup
```

```
#download and move the backup script to /root , secure it, and  
allow execution  
wget http://www.bradynd.com/fullbackup3.sh  
sudo mv fullbackup3.sh /root  
sudo chown root:root /root/fullbackup3.sh  
sudo chmod 700 /root/fullbackup3.sh
```

```
#edit file /root/dailybackup3.sh:  
sudo jed /root/fullbackup3.sh  
#edit the below DVDDEVICE line to what the  
#device for the DVD writer is. In the appliance (3.0.0)  
#it should be '/dev/scd0'.  
DVDDEVICE=/dev/scd0
```

```
#edit full name you entered above for encryption key:  
YOURFULLNAME='Brady Miller'  
TEXT EDITOR SAVE AND EXIT
```

```
#Automate script to cron for a daily run at 1:02 AM. WARNING:  
This script needs to finish and start on the same day since it  
plays around with file names using the date command.  
Basically, don't start this script before midnight unless you are  
sure it will finish before midnight. This is why I have it set for  
1:02AM.
```

```
export EDITOR=/usr/bin/jed  
sudo crontab -e
```

```
#paste below line at end of file (also ensure you add a new  
line(enter key) after this line):  
02 1 * * * /root/fullbackup3.sh  
TEXT EDITOR SAVE AND EXIT
```

Static IP Address Setup

[Main TOC Link](#)

1. These are instructions for setting up a static IP address for your appliance using Webmin.
2. First, you should record the required IP addresses (example form below). The 'Appliance IP Address' is going to be the IP address of your appliance (within your network). The 'Subnet Mask' is 255.255.255.0 in most cases. The 'Broadcast IP Address' can be calculated by comparing the 'Appliance IP Address' and the 'Subnet Mask'. For example, if the 'Appliance IP Address' is 192.168.1.114 and the 'Subnet Mask' is 255.255.255.0, then the 'Broadcast IP Address' is 192.168.1.255. There is also a Subnet calculator that can calculate the 'Broadcast IP Address' at <http://www.subnet-calculator.com/> . The 'Gateway IP Address' is the IP address of your gateway. The 'DNS server IP Address' entries are the IP addresses of your DNS servers (the DNS server IP addresses are generally supplied by your internet service providers, and there are usually two of them).

Appliance IP Address: _____

Subnet Mask: _____

Broadcast IP Address: _____

Gateway IP Address: _____

DNS server IP Address: _____

DNS server IP Address: _____

3. Point a web browser outside your appliance to the Webmin link reported in your appliance [introduction](#) screen.

(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Login.

Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox

File Edit View History Delicious Tools Help

https://192.168.1.167:1

Webmin 1.450 on openemr (Ubu... x

Login: openemr

- Webmin
- System
- Servers
- Others
- Networking
- Hardware
- Cluster
- Un-used Modules

Search:

- View Module's Logs
- System Information
- Refresh Modules
- Logout

System
hostname openemr

Operating system
Ubuntu Linux 8.04.2

Webmin version
1.450

Time on system
Sat Feb 28 09:33:21 2009

Kernel and CPU
Linux 2.6.24-23-server on i686

System uptime
8 hours, 6 minutes

CPU load averages
0.16 (1 min) 0.03 (5 mins) 0.07 (15 mins)

Real memory
503.36 MB total, 104.82 MB used

Virtual memory
1.44 GB total, 88 kB used

Local disk space
77.94 GB total, 5.35 GB used

Done 192.168.1.167:10000

Click 'Networking'.

Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox

File Edit View History Delicious Tools Help

https://172.16.0.113:10000/

Webmin 1.450 on openemr (Ubu... x

Login: openemr

- Webmin
- System
- Servers
- Others
- Networking**
 - Bandwidth Monitoring
 - Linux Firewall
 - NIS Client and Server
 - Network Configuration
 - TCP Wrappers
- Hardware
- Cluster
- Un-used Modules

Search:

View Module's Logs

System Information

Refresh Modules

Logout

webmin


System hostname	openemr
Operating system	Ubuntu Linux 8.04.2
Webmin version	1.450
Time on system	Mon Mar 2 14:23:18 2009
Kernel and CPU	Linux 2.6.24-23-server on i686
System uptime	2 hours, 25 minutes
CPU load averages	0.00 (1 min) 0.00 (5 mins) 0.00 (15 mins)
Real memory	503.36 MB total, 84.20 MB used
Virtual memory	1.44 GB total, 0 bytes used
Local disk space	77.94 GB total, 5.35 GB used

https://172.16.0.113:10000/net/ 172.16.0.113:10000


Click 'Network Configuration'.




Click 'Network Interfaces'.




Click the 'Activated at Boot' tab.




Click 'eth0'.



- 1) Toggle on 'Static configuration'.
- 2) Enter 'Appliance IP Address' into 'IP Address' field.
- 3) Enter 'Subnet Mask' into 'Netmask' field.
- 4) Enter 'Broadcast IP Address' into 'Broadcast' field.
- 5) Click 'Save'.



Click 'Return to network configuration'.




Click 'Routing and Gateways'.



- 1) Toggle on 'Gateway'
- 2) Enter the 'Gateway IP Address' into 'Gateway' field
- 3) Click 'Save'.



Click 'Hostname and DNS client'.



Enter the 'DNS server IP Address' values into the 'DNS servers' fields, then click 'Save'.



Click 'System Information'.

4. Then reboot the appliance per the instructions found in the '[Reboot or Shutdown Appliance](#)' section.

Change Clock

[Main TOC Link](#)

1. These are instructions on changing the time in your appliance using Webmin.
2. Point a web browser outside your appliance to the Webmin link reported in your appliance [introduction](#) screen.

(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Login.



Click 'Hardware'.

The screenshot displays the Webmin 1.450 web interface. The browser window title is "Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox". The page content includes a sidebar on the left with a tree view of modules: Login, Webmin, System, Servers, Others, Networking, Hardware (with sub-items: GRUB Boot Loader, Partitions on Local Disks, Printer Administration, System Time), Cluster, and Un-used Modules. A mouse cursor is pointing at the "System Time" link. Below the sidebar are links for "View Module's Logs", "System Information", "Refresh Modules", and "Logout". The main content area features the Webmin logo and a system information table:

System hostname	openemr
Operating system	Ubuntu Linux 8.04.2
Webmin version	1.450
Time on system	Mon Mar 2 03:05:53 2009
Kernel and CPU	Linux 2.6.24-23-server on i686
CPU load averages	0.00 (1 min) 0.06 (5 mins) 0.07 (15 mins)
Real memory	503.36 MB total, 66.90 MB used
Virtual memory	1.44 GB total, 0 bytes used
Local disk space	77.94 GB total, 5.35 GB used

At the bottom of the main content area, a warning message states: "Warning - Your system is actually running Ubuntu Linux version 5.2.4". The browser's status bar at the bottom shows "Done" and the IP address "192.168.1.141:10000".

Click 'System Time'.



Set the time and timezone of your appliance here. Do **NOT** set up a 'time server sync'; this will screw up your appliance.

Change Appliance Password


[Main TOC Link](#)

1. These are instructions for changing the password to the 'openemr' user in your appliance using Webmin. This is important to secure your appliance. It will effectively change the 'openemr' user password for logging into Webmin, logging into your appliance's commandline, and to confirm usage of the 'sudo' command.
2. Point a web browser outside your appliance to the Webmin link reported in your appliance [introduction](#) screen.


(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Login.



Click 'System'



Click 'Change Passwords'.



Click 'openemr'.



Type and confirm new password, then click 'change'

Reboot or Shutdown Appliance

[Main TOC Link](#)

1. These are instructions on how to shutdown or restart your appliance using Webmin.
2. Point a web browser outside your appliance to the Webmin link reported in your appliance [introduction](#) screen.

(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Login.

The screenshot displays the Webmin 1.450 web interface. The browser window title is "Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox". The interface includes a menu bar (File, Edit, View, History, Delicious, Tools, Help) and a tab bar with three tabs: "Login", "Webmin 1.450 on openemr (Ubu...", and "OpenEMR, 2.8.3 Appliance Manual".

On the left sidebar, the "Login: openemr:" section contains a list of modules: Webmin, System, Servers, Others, Networking, Hardware, Cluster, and Un-used Modules. A search box is located below this list. Further down, there are links for "View Module's Logs", "System Information", "Refresh Modules", and "Logout".

The main content area features the Webmin logo and a system information table:

System hostname	openemr
Operating system	Ubuntu Linux 8.04.2
Webmin version	1.450
Time on system	Mon Mar 2 02:37:20 2009
Kernel and CPU	Linux 2.6.24-23-server on i686
System uptime	2 hours, 0 minutes
CPU load averages	0.00 (1 min) 0.00 (5 mins) 0.00 (15 mins)
Real memory	503.36 MB total, 73.87 MB used
Virtual memory	1.44 GB total, 0 bytes used
Local disk space	77.94 GB total, 5.35 GB used

At the bottom of the browser window, the status bar shows "Done" on the left and the IP address "192.168.1.141:10000" on the right.

Click 'System'.

Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox

File Edit View History Delicious Tools Help

Login: openemr

- Webmin
- System
 - Bootup and Shutdown
 - Change Passwords
 - Disk and Network
 - Filesystems
 - Filesystem Backup
 - Log File Rotation
 - MIME Type Programs
 - PAM Authentication
 - Running Processes
 - Scheduled Commands
 - Scheduled Cron Jobs
 - Software Packages
 - System Documentation
 - System Logs
 - Users and Groups
- Servers
- Others
- Networking
- Hardware
- Cluster
- Un-used Modules

Search:

View Module's Logs

Custom Information

Done

192.168.1.141:10000

System hostname openemr

Operating system Ubuntu Linux 8.04.2

Webmin version 1.450

Time on system Mon Mar 2 02:37:20 2009

Kernel and CPU Linux 2.6.24-23-server on i686

System uptime 2 hours, 0 minutes


CPU load averages 0.00 (1 min) 0.00 (5 mins) 0.00 (15 mins)

Real memory 503.36 MB total, 73.87 MB used

Virtual memory 1.44 GB total, 0 bytes used

Local disk space 77.94 GB total, 5.35 GB used

Click 'Bootup and Shutdown'.



Scroll to bottom of page. To reboot your appliance, click the 'Reboot System' button. To shutdown your appliance, click the 'Shutdown System' button. You will be asked to confirm this on the next screen.

Desktop Installation

[Main TOC Link](#)

1. This is for those wimps whom are having difficulty with administration of the appliance via commandline and/or Webmin. These are instructions to install the KDE desktop (includes all the thrills such as OpenOffice etc.) on your appliance. This will increase the size of your appliance by 1.6 GB.
2. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then type in your user password):

```
#install kubuntu desktop  
sudo apt-get install kubuntu-desktop
```

```
-enter Y to continue
-(this will take awhile)
#install the x-windows manager and start it
sudo apt-get install gdm
-enter Y to continue
-enter 'ok'
-select 'kdm'

#restart computer (will now boot into the KDE desktop)
sudo shutdown -r now
```

Instructions for Building the OpenEMR Appliance

[Main TOC Link](#)

[LINK TO MANUAL IN PDF FORMAT](#)

Instructions for Building the OpenEMR Appliance Chapter Index

Instructions for Building the OpenEMR Appliance	66
Software	66
Install the Ubuntu 8.04 Server Virtual Computer	66
Configure PHP and Apache (with SSL)	98
Install OpenEMR 3.0.1	99
Install and Configure Webmin	110
Configure Firewall	114
Finishing Touches On Appliance	125

Software

[Main TOC Link](#)

[Chapter Index Link](#)


1. Ubuntu Server Edition (8.04)
2. Apache (2.2.8), MySQL (5.0.51a), and PHP (5.2.4)
3. Webmin (1.470)
4. OpenEMR (3.0.1)

Install the Ubuntu 8.04 Server Virtual Computer

[Main TOC Link](#)

[Chapter Index Link](#)


1. You can use either VMware Workstation or VMware Server to build the Ubuntu 8.04 Server Appliance.
2. Download Ubuntu Server Edition 8.04 installation ISO file from <http://www.ubuntu.com/getubuntu/download> .
3. Ubuntu Server Edition 8.04 Appliance Installation with VMware Workstation version 6.5:




Click 'New Virtual Machine'.



Select 'Typical', then Click 'Next'.




Browse and select ubuntu-8.04.2-server-i386.iso file, then click 'Next'.




Type in name of appliance and location to save it to, then click 'Next'. I typed OpenEMR-3-0-1-appliance-1.




Set maximum disk size to 80GB, select 'Split virtual disk into 2GB files', then click 'Next'.




Click 'Network Adapter'.




Select 'Bridged: Connected directly to the physical network' and check 'Replicate physical network connection state', then click 'OK'.




Click 'Finish'.




Click 'Power on this virtual machine'.




Select language.




Select 'Install Ubuntu Server'.




Select language.




Select country.




Select 'Yes' to detect keyboard layout.




Go through bunch of screens like above to figure out keyboard.




Select 'Continue' if detected correct keyboard.




Type 'openemr' for Hostname, and then 'Continue'.




Select time zone, I chose 'Pacific'.




Select 'Guided - use entire disk'.




Select the highlighted disk.




Select 'Yes'.




Type 'Openemr Appliance', then 'Continue'.




Type 'openemr', then 'Continue'.




Choose a password. I typed 'openemrcool' for password, then 'Continue'.




Confirm password 'openemrcool', then 'Continue'.




Leave blank and 'Continue'.




Select 'LAMP server', 'OpenSSH server', and 'Print Server'; then click 'Continue'.




Leave blank and 'Continue'.




Leave blank and 'Continue'.



Leave blank and 'Continue'.



Click 'Continue'.



login with user:openemr pass:openemrcool

4. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

#update and upgrade ubuntu

```
sudo apt-get update  
sudo apt-get upgrade  
-enter Y to continue
```


#Install the php command line, imagemagick, lynx client browser, and jed text editor.

```
sudo aptitude install jed lynx php5-cli imagemagick  
-enter Y to continue
```

#get packages required by Vmware Tools

```
sudo aptitude install build-essential linux-headers-$(uname -r)  
-enter Y to continue
```

5. Prepare to install Vmware Tools:



Click 'VM' in top menu, and select 'Install VMware Tools...'.
To direct input to this VM, click inside or press Ctrl+G.

6. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

```
#mount the vmware drive
```

```
sudo mkdir /mnt/temp  
sudo mount /dev/cdrom /mnt/temp
```

```
#get and unpackage vmware tools
```

```
cp /mnt/temp/VMwareTools-*.tar.gz .  
tar -zxpf VMwareTools-*.tar.gz
```

```
#install Vmware Tools
```

```
cd vmware-tools-distrib  
sudo ./vmware-install.pl  
-hit 'enter' to select default for all questions
```

```
#clean up files
```

```
cd ..  
rm -f VMwareTools-*.tar.gz  
rm -fr vmware-tools-distrib
```

```
#unmount the vmware drive
```

```
sudo umount /dev/cdrom  
sudo rm -fr /mnt/temp
```

Configure PHP and Apache (with SSL)

[Main TOC Link](#)

[Chapter Index Link](#)

1. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

```
#edit the php config file /etc/php5/apache2/php.ini
```

```
sudo jed /etc/php5/apache2/php.ini
```

```
#edit following variables:
```

```
short_open_tag = On
```

```
max_execution_time = 60
```

```
max_input_time = 90
```

```
memory_limit = 128M
```

```
display_errors = Off
```

```
log_errors = On
```

```
register_globals = Off
```

```
post_max_size = 30M
```

```
magic_quotes_gpc = On
```

```
file_uploads = On
```

```
upload_max_filesize = 30M
```

```
TEXT EDITOR SAVE AND EXIT
```

```
#edit apache2 config file /etc/apache2/apache2.conf
```

```
sudo jed /etc/apache2/apache2.conf
```

```
#Paste below to end of file:
```

```
<Directory "/var/www/openemr/documents">
```

```
order deny,allow
```

```
Deny from all
```

```
</Directory>
```

```
<Directory "/var/www/openemr/edi">
```

```
order deny,allow
```

```
Deny from all
```

```
</Directory>
```

```
<Directory "/var/www/openemr/era">
```

```
order deny,allow
```

```
Deny from all
```

```
</Directory>
```

```
TEXT EDITOR SAVE AND EXIT
```

```
#create an SSL certificate
```

```
sudo openssl req @$@ -new -x509 -days 1825 -nodes
```

```
-out /etc/apache2/apache.pem -keyout
```

```
/etc/apache2/apache.pem
```

```
-ok to just select all defaults
```

```

#configure SSL in apache2
sudo a2enmod ssl
sudo cp /etc/apache2/sites-available/default
    /etc/apache2/sites-available/ssl
sudo ln -s /etc/apache2/sites-available/ssl /etc/apache2/
    sites-enabled/

#edit file /etc/apache2/sites-available/default
sudo jed /etc/apache2/sites-available/default
#Edit first two lines of file:
NameVirtualHost *:80
<VirtualHost *:80>
TEXT EDITOR SAVE AND EXIT

#edit file /etc/apache2/sites-available/default
sudo jed /etc/apache2/sites-available/ssl
#Edit first two lines of file:
NameVirtualHost *:443
<VirtualHost *:443>

#Insert the below code right above the 'LogLevel warn'
line:
SSLEngine on
SSLCertificateFile /etc/apache2/apache.pem
TEXT EDITOR SAVE AND EXIT

#edit file /etc/apache2/mods-available/ssl.conf
sudo jed /etc/apache2/mods-available/ssl.conf
#Uncomment the following lines (near end of file):
SSLCipherSuite HIGH:MEDIUM:!ADH
SSLProtocol all -SSLv2
TEXT EDITOR SAVE AND EXIT

#restart apache
sudo /etc/init.d/apache2 restart
-do not worry about the domain name messages

```

Install OpenEMR 3.0.1

[Main TOC Link](#)
[Chapter Index Link](#)

1. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

```

#Download OpenEMR
wget http://downloads.sourceforge.net/openemr/openemr-3.0.1.tar.gz

```

```
#Put the OpenEMR program in its place
sudo tar -pxzvf openemr-3.0.1.tar.gz
sudo rm -f openemr-3.0.1.tar.gz
sudo mv openemr-3.0.1 /var/www/openemr
sudo chown -R root:root /var/www/openemr
```

```
#Deal with file permissions
sudo chmod 666 /var/www/openemr/library/sqlconf.php
sudo chmod 666 /var/www/openemr/interface/globals.php
sudo chmod 666 /var/www/openemr/gacl/gacl.ini.php
sudo chmod 666 /var/www/openemr/gacl/gacl.class.php
sudo chown -R www-data:www-data
    /var/www/openemr/documents
sudo chown -R www-data:www-data /var/www/openemr/edi
sudo chown -R www-data:www-data /var/www/openemr/era
sudo chown -R www-data:www-data
    /var/www/openemr/custom/letter_templates
sudo chown -R www-data:www-data
    /var/www/openemr/gacl/admin/templates_c
sudo chown -R www-data:www-data
    /var/www/openemr/library/freeb
sudo chown -R www-data:www-data
    /var/www/openemr/interface/main/calendar/modules/PostCa
    lendar/pntemplates/cache
sudo chown -R www-data:www-data
    /var/www/openemr/interface/main/calendar/modules/PostCa
    lendar/pntemplates/compiled
```

```
#Get IP address of appliance
sudo ifconfig
-Look at screenshot below to get IP address
```

```
OpenEMR-3-0-0-appliance-1 - VMware Workstation
File Edit View VM Team Windows Help
Home x OpenEMR-3-0-0-appliance... x
Powered On
OpenEMR
OpenEMR
Favorites
To access official Ubuntu documentation, please visit:
http://help.ubuntu.com/
openemr@openemr:~$ sudo ifconfig
[sudo] password for openemr:
eth0      Link encap:Ethernet  HWaddr 00:0c:29:08:80:5a
          inet addr:192.168.1.167  Bcast:192.168.1.255  Mask:255.255.255.0
          inet6 addr: fe80::20c:29ff:fe08:805a/64 Scope:Link
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:82946 errors:0 dropped:0 overruns:0 frame:0
          TX packets:49309 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:100206481 (103.1 MB)  TX bytes:4477747 (4.2 MB)
          Interrupt:17 Base address:0x2000


lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          inet6 addr: ::1/128 Scope:Host
          UP LOOPBACK RUNNING  MTU:16436  Metric:1
          RX packets:106 errors:0 dropped:0 overruns:0 frame:0
          TX packets:106 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:10258 (10.0 KB)  TX bytes:10258 (10.0 KB)

openemr@openemr:~$ _
To direct input to this VM, click inside or press Ctrl+G.
```

The location where you will find the IP address of your appliance is circled in red above.

3. Now, open a webbrowser outside the appliance and point to (the APPLIANCE_IP_ADDRESS was found by above [ifconfig](#) command): https://APPLIANCE_IP_ADDRESS/openemr/setup.php

(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Click 'Continue'.



Select 'Have setup create the database', then click 'Continue'.

OpenEMR Setup Tool - Mozilla Firefox

File Edit View History Delicious Tools Help

OpenEMR Setup Tool

OpenEMR Setup

Step 2

Now you need to supply the MySQL server information and path information. Detailed instructions on each item can be found in the ['INSTALL'](#) manual file.

MYSQL SERVER:

Server Host: (If you run MySQL and Apache/PHP on the same computer, then leave this as 'localhost'. If they are on separate computers, then enter the IP address of the computer running MySQL.)

Server Port: (This is the MySQL port. The default port for MySQL is 3306.)

Database Name: (This is the name of the OpenEMR database in MySQL - 'openemr' is the recommended)

Login Name: (This is the name of the OpenEMR login name in MySQL - 'openemr' is the recommended)

Password: (This is the Login Password for when PHP accesses MySQL - it should be at least 8 characters long and composed of both numbers and letters)

Name for Root Account: (This is name for MySQL root account. For localhost, it is usually ok to leave it 'root'.)

Root Pass: (This is your MySQL root password. For localhost, it is usually ok to leave it blank.)

User Hostname: (If you run Apache/PHP and MySQL on the same computer, then leave this as 'localhost'. If they are on separate computers, then enter the IP address of the computer running Apache/PHP.)

OPENEMR USER:

Initial User: (This is the login name of user that will be created for you. Limit this to one word.)

Initial User's Name: (This is the real name of the 'initial user'.)

Initial Group: (This is the group that will be created for your users. This should be the name of your practice.)


OPENEMR PATHS:

Absolute Path: (This is the full absolute directory path to openemr. The value here is automatically created, and should not need to be modified. Do not worry about direction of slashes; they will be automatically corrected.)


Relative HTML Path: (Set this to the relative html path, ie. what you would type into the web browser after the server address to get to OpenEMR. For example, if you type 'http://127.0.0.1/clinic/openemr/' to load OpenEMR, set this to '/clinic/openemr' without the trailing slash. Do not worry about direction of slashes; they will be automatically corrected.)

Done 192.168.1.167


For my appliance I typed 'openemr' into 'Password' field, and otherwise kept defaults. Click 'Continue'.




Click 'Continue'.




Click 'Continue'.




We have already configured this in the above '[Configure PHP and Apache \(with SSL\)](#)' section. Click 'Continue'.



We have already configured this in the above '[Configure PHP and Apache \(with SSL\)](#)' section. Click 'Continue'.



Click 'Click here to start using OpenEMR' to go to OpenEMR.



Continue to below instructions.

4. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

```
#Re-secure files  
sudo chmod 644 /var/www/openemr/library/sqlconf.php  
sudo chmod 644 /var/www/openemr/interface/globals.php  
sudo chmod 644 /var/www/openemr/gacl/gacl.ini.php  
sudo chmod 644 /var/www/openemr/gacl/gacl.class.php
```

Install and Configure Webmin

[Main TOC Link](#)

[Chapter Index Link](#)

1. Webmin is an awesome way to administer a ubuntu server with a graphical interface remotely.

2. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

```
#download Webmin
```

```
wget http://prdownloads.sourceforge.net/webadmin/webmin_1.470_all.deb
```

```
#install Webmin
```

```
sudo dpkg -i webmin_1.470_all.deb
```

```
-IGNORE the dependency errors (below command will install)
```

```
sudo apt-get install -f
```

```
-enter 'Y' to continue
```

```
rm -f webmin_1.460_all.deb
```

1. Now, open a webbrowser outside the appliance and point to (the APPLIANCE_IP_ADDRESS was found by above [ifconfig](#) command):
`https://APPLIANCE_IP_ADDRESS:10000/`

(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Login with user:'openemr' and pass:'openemrcool'.

Webmin 1.460 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox

File Edit View History Delicious Tools Help

https://192.168.1.167:10000/

Webmin 1.460 on openemr (Ubu... x

Login: openemr

- Webmin
- System
- Servers
- Others
- Networking
- Hardware
- Cluster
- Un-used Modules

Search:

- View Module's Logs
- System Information
- Refresh Modules
- Logout

System hostname: openemr
Operating system: Ubuntu Linux 8.04.2
Webmin version: 1.460
Time on system: Mon Mar 16 02:02:46 2009
Kernel and CPU: Linux 2.6.24-23-server on i686
CPU load averages: 0.18 (1 min) 0.15 (5 mins) 0.10 (15 mins)
Real memory: 503.36 MB total, 97.77 MB used
Virtual memory: 1.44 GB total, 96 kB used
Local disk space: 77.94 GB total, 5.41 GB used


The 2 following Webmin module updates are now available ..

Module	Version	Fixes problem
System and Server Status	1.461	All Remote TCP Service monitors report that the service is not installed
File Manager	1.461	Opening the file manager module fails with an error about un-trusted referers


[Install Updates Now](#)

Done 192.168.1.167:10000

Click 'Install Updates Now' button.



Scroll to bottom of window and click 'Return to Webmin configuration'.



Click 'Logout'.

Configure Firewall

[Main TOC Link](#)

[Chapter Index Link](#)

1. We will only allow access to the appliance through ports 22 (SSH), 443 (OpenEMR via https), and 10000 (Webmin via https). Note that we are blocking the http port (80) to force users to use https (encrypted) when connecting to OpenEMR.
2. Open a webbrowser outside the appliance and point to (the APPLIANCE_IP_ADDRESS was found by above [ifconfig](#) command):
`https://APPLIANCE_IP_ADDRESS:10000/`

(If you are getting a certificate security error, then first follow the instructions in below appendix section '[Configuring client web browser for https](#)' to configure your web browser.)



Login with user:'openemr' and pass:'openemrcool'.

Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) - Mozilla Firefox

File Edit View History Delicious Tools Help

https://192.168.1.167:1

Webmin 1.450 on openemr (Ubu... x

Login: openemr

- Webmin
- System
- Servers
- Others
- Networking
- Hardware
- Cluster
- Un-used Modules

Search:

- View Module's Logs
- System Information
- Refresh Modules
- Logout

System
hostname openemr

Operating system
Ubuntu Linux 8.04.2

Webmin version
1.450

Time on system
Sat Feb 28 09:33:21 2009

Kernel and CPU
Linux 2.6.24-23-server on i686

System uptime
8 hours, 6 minutes

CPU load averages
0.16 (1 min) 0.03 (5 mins) 0.07 (15 mins)

Real memory
503.36 MB total, 104.82 MB used

Virtual memory
1.44 GB total, 88 kB used

Local disk space
77.94 GB total, 5.35 GB used

Done 192.168.1.167:10000

Click 'Networking'.

The screenshot displays the Webmin 1.450 interface in a Mozilla Firefox browser window. The browser's address bar shows the URL `https://192.168.1.167:1`. The page title is "Webmin 1.450 on openemr (Ubuntu Linux 8.04.2)".

Left Sidebar:

- Login: openemr
- Webmin
- System
- Servers
- Others
- Networking** (highlighted)
- Bandwidth Monitoring
- Linux Firewall (mouse cursor pointing here)
- NIS Client and Server
- Network Configuration
- TCP Wrappers
- Hardware
- Cluster
- Un-used Modules
- Search:
- View Module's Logs
- System Information
- Refresh Modules
- Logout


Right Panel (System Information):

- System hostname:** openemr
- Operating system:** Ubuntu Linux 8.04.2
- Webmin version:** 1.450
- Time on system:** Sat Feb 28 09:33:21 2009
- Kernel and CPU:** Linux 2.6.24-23-server on i686
- System uptime:** 8 hours, 6 minutes
- CPU load averages:** 0.16 (1 min) 0.03 (5 mins) 0.07 (15 mins)
- Real memory:** 503.36 MB total, 104.82 MB used
- Virtual memory:** 1.44 GB total, 88 kB used
- Local disk space:** 77.94 GB total, 5.35 GB used

Bottom Status Bar:

`javascript:toggleview('net','togglenet')` | 192.168.1.167:10000

Click 'Linux Firewall'.



Select 'Block all except SSH and IDENT on external interface'. Select the 'eth0' interface from the menu next to this. Toggle on the 'Enable firewall at boot time?'. Then click the 'Setup Firewall' button.

Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) Mozilla Firefox

File Edit View History Delicious Tools Help

Webmin 1.450 on openemr (Ubuntu Linux 8.04.2) x

Login: openemr

- Webmin
- System
- Servers
- Others
- Networking
 - Bandwidth Monitoring
 - Linux Firewall
 - NIS Client and Server
 - Network Configuration
 - TCP Wrappers
- Hardware
- Cluster
- Un-used Modules

Search:

View Module's Logs

System Information

Refresh Modules

Logout

Help: Linux Firewall

Module Config

Rules file: /etc/iptables.up.rules

Showing IPTable: Packet filtering (filter) Add a new chain named:

Incoming packets (INPUT)

Select all | Invert selection

Action	Condition	Move	Add
<input type="checkbox"/> Accept	If input interface is not eth0	↓	↓ ↑
<input type="checkbox"/> Accept	If protocol is TCP and TCP flags ACK (of ACK) are set	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If state of connection is ESTABLISHED	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If state of connection is RELATED	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is UDP and destination port is 1024:65535 and source port is 53	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is ICMP and ICMP type is echo reply	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is ICMP and ICMP type is destination-unreachable	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is ICMP and ICMP type is source-quench	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is ICMP and ICMP type is time-exceeded	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is ICMP and ICMP type is parameter-problem	↓ ↑	↓ ↑
<input type="checkbox"/> Accept	If protocol is TCP and destination port is 22	↓ ↑	↓ ↑
<input checked="" type="checkbox"/> Accept	If protocol is TCP and destination port is auth	↑	↓ ↑

Select all | Invert selection

Set Default Action To: Drop Delete Selected Add Rule

Forwarded packets (FORWARD)

There are no rules defined for this chain.

Set Default Action To: Accept Add Rule

Outgoing packets (OUTPUT)

There are no rules defined for this chain.

Set Default Action To: Accept Add Rule

Apply Configuration Click this button to make the firewall configuration listed above active. Any firewall rules currently in effect will be flushed and replaced.


Revert Configuration Click this button to reset the configuration listed above to the one that is currently active.

Activate at boot Yes No Change this option to control whether your firewall is activated at boot time or not.


Reset Firewall Click this button to clear all existing firewall rules and set up new rules for a basic initial configuration.

Done 192.168.1.167:10000


Select the line circled in red above. Then click the 'Delete Selected' button.




Click the 'Add Rule' button circled in red above.




All places that require input are circled in red. Type 'SSL' in 'Rule comment'. Toggle on the 'Accept' in 'Action to take'. In 'Network protocol', select 'Equals'. In 'Destination TCP or UDP port', select 'Equals' and type '443' for 'Port(s)'. Then click the 'Create' button.




Click the 'Add Rule' button circled in red above.



All places that require input are circled in red. Type 'webmin' in 'Rule comment'. Toggle on the 'Accept' in 'Action to take'. In 'Network protocol', select 'Equals'. In 'Destination TCP or UDP port', select 'Equals' and type '10000' for 'Port(s)'. Then click the 'Create' button.



Click the 'Apply Configuration' button.



Click 'Logout'.

Finishing Touches On Appliance

[Main TOC Link](#)

[Chapter Index Link](#)

1. We will install a startup/shutdown script. On startup it will configure the introductory screen to give the user required information (IP address, login names/passwords, etc.). On shutdown it will reset the network card to ensure mobility of the virtual appliance.
2. Enter below **bolded** instructions on command line (if prompted to give password during the sudo command, then use 'openemrcool'):

#download the script

sudo wget http://www.bradymd.com/openemrApplianceScript


#install the script

```
sudo mv openemrApplianceScript /etc/init.d/  
sudo chown root:root /etc/init.d/openemrApplianceScript  
sudo chmod +x /etc/init.d/openemrApplianceScript  
sudo update-rc.d openemrApplianceScript defaults 99
```

#shutdown the appliance

```
sudo shutdown -h now
```

1. In Vmware, need to set the CD/DVD drive to autosect.




Double-click 'CD/DVD (IDE)'.




Select 'Use physical drive' and select 'Auto Detect' from menu. Then click 'OK'.


1. Because this appliance was built with VMware Workstation 6.5, we now need to convert the appliance to an earlier version to ensure compatibility with all VMware Player and VMware Server versions. This is done with free software by VMware, called 'VMware vCenter Converter Standalone Client'.
 1. Ensure VMware Workstation is closed.
 2. Download, install, and start the 'VMware vCenter Converter Standalone Client' from vmware.com (it is free).




Click 'Convert Machine'.




Click 'Select source type:' field.




Select 'VMware workstation or other VMware virtual machine'.




Select the 'virtual machine file:', then click 'Next'.




Click 'Select VMware product:' field.




Select 'VMware Workstation 5.x'.




Click 'Next'.



Click the 'Data to copy' field.



Select '2 GB split not pre-allocated', then click 'Next'.



Click 'Finish'.

ALL DONE

Appendix

[Main TOC Link](#)


A. Configuring client web browser for https

[Main TOC Link](#)

1. For security, this appliance forces users to use https (encrypted) over a web browser. Because we are using a homemade security certificate (real certificates cost money), most new web browsers will give a security error. This can easily be dealt with by following the browser instructions to create an exception. I have posted steps for



Click the 'Add Exception...' button.



Click the 'Get Certificate' button. (DO NOT edit the 'Location:')



Click 'Confirm Security Exception'. Ensure 'Permanently store this exception' is checked, so you don't have to go through this every time. Also, DO NOT change 'Location:'.

ALL DONE, go back and continue your previous instructions.

3. Internet Explorer:



Click 'Continue to this website'.

ALL DONE, go back and continue your previous instructions.

B. Useful Websites

[Main TOC Link](#)

OpenEMR links:

1. <http://www.oemr.org/> (Main OpenEMR website with a good Wiki and a new forum)
2. <http://sourceforge.net/projects/openemr/> (Main OpenEMR forums are here)
3. <http://www.bradynd.com/appliance/> (OpenEMR Virtual Appliance Homepage)

Virtual Machine links:

1. <http://www.vmware.com/> (VMware website)
2. <http://www.vmware.com/appliances/> (VMware virtual appliance explanation)
3. <http://www.vmware.com/vmtn/appliances/overview.html> (Another VMware virtual appliance explanation)

General EMR links:

1. <http://www.linuxmednews.com/> (Open Source EMR news)
2. <http://www.emrupdate.com/> (Great site and forums which discusses proprietary and open source EMRs. It also has a great actively updated price comparison for most proprietary EMR's)
3. <http://ehr.gplmedicine.org/> (Great detailed reviews of OpenEMR, MirrorMed, and FreeMed)
4. <http://www.bradynd.com/> (Installation instructions and quick reviews of OpenEMR, MirrorMed, FreeMed, and VistA.)

C. Author Email and License/Disclaimer

[Main TOC Link](#)

Author: Brady Miller

Email:brady@sparmy.com

www.bradynd.com

Copyright (C) <2006-2009> <Brady Miller>

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

GNU GENERAL PUBLIC LICENSE
Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc.
51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA
Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users. This

General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Lesser General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

GNU GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".

Activities other than copying, distribution and modification are not

covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

- a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.
- b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.
- c) If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of

a storage or distribution medium does not bring the other work under the scope of this License.

3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:

- a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
- b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
- c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.

6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.

7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of

this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

```
<one line to give the program's name and a brief idea of what it does.>  
Copyright (C) <year> <name of author>
```

```
This program is free software; you can redistribute it and/or modify  
it under the terms of the GNU General Public License as published by  
the Free Software Foundation; either version 2 of the License, or  
(at your option) any later version.
```

```
This program is distributed in the hope that it will be useful,  
but WITHOUT ANY WARRANTY; without even the implied warranty of  
MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
```

GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this when it starts in an interactive mode:

```
Gnomovision version 69, Copyright (C) year name of author
Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type `show w'.
This is free software, and you are welcome to redistribute it
under certain conditions; type `show c' for details.
```

The hypothetical commands `show w' and `show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than `show w' and `show c'; they could even be mouse-clicks or menu items--whatever suits your program.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the program, if necessary. Here is a sample; alter the names:

```
Yoyodyne, Inc., hereby disclaims all copyright interest in the program
`Gnomovision' (which makes passes at compilers) written by James Hacker.
```

```
<signature of Ty Coon>, 1 April 1989
Ty Coon, President of Vice
```

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License.